



#### **Computer-System Operation**

- I/O devices and the CPU can execute concurrently.
- Each device controller is in charge of a particular device type.
- Each device controller has a local buffer.
- CPU moves data from/to main memory to/from local buffers
- I/O is from the device to local buffer of controller.
- Device controller informs CPU that it has finished its operation by causing an *interrupt*.

Operating System Concepts

2.3

Silberschatz, Galvin and Gagne ©2002



# C

## **Common Functions of Interrupts**

- Interrupt transfers control to the interrupt service routine generally, through the *interrupt vector*, which contains the addresses of all the service routines.
- Interrupt architecture must save the address of the interrupted instruction.
- Incoming interrupts are *disabled* while another interrupt is being processed to prevent a *lost interrupt*.
- A *trap* is a software-generated interrupt caused either by an error or a user request.
- An operating system is *interrupt* driven.




## **Interrupt Handling**

- The operating system preserves the state of the CPU by storing registers and the program counter.
- Determines which type of interrupt has occurred:
  - polling
  - vectored interrupt system
- Separate segments of code determine what action should be taken for each type of interrupt

Operating System Concepts

2.5

Silberschatz, Galvin and Gagne ©2002







#### I/O Structure

- After I/O starts, control returns to user program only upon I/O completion.
  - Wait instruction idles the CPU until the next interrupt
  - Wait loop (contention for memory access).
  - At most one I/O request is outstanding at a time, no simultaneous I/O processing.
- After I/O starts, control returns to user program without waiting for I/O completion.
  - System call request to the operating system to allow user to wait for I/O completion.
  - Device-status table contains entry for each I/O device indicating its type, address, and state.
  - Operating system indexes into I/O device table to determine device status and to modify table entry to include interrupt.

Silberschatz, Galvin and Gagne ©2002

Operating System Concepts





## Direct Memory Access Structure

- Used for high-speed I/O devices able to transmit information at close to memory speeds.
- Device controller transfers blocks of data from buffer storage directly to main memory without CPU intervention.
- Only on interrupt is generated per block, rather than the one interrupt per byte.



### **Storage Structure**


- Main memory only large storage media that the CPU can access directly.
- Secondary storage extension of main memory that provides large nonvolatile storage capacity.
- Magnetic disks rigid metal or glass platters covered with magnetic recording material
  - Disk surface is logically divided into tracks, which are subdivided into sectors.
  - The disk controller determines the logical interaction between the device and the computer.


Operating System Concepts


2.1


Silberschatz, Galvin and Gagne ©2002
















#### **Hardware Protection**

- Dual-Mode Operation
- I/O Protection
- Memory Protection
- CPU Protection

Operating System Concepts

2.17

Silberschatz, Galvin and Gagne ©2002






## **Dual-Mode Operation**

- Sharing system resources requires operating system to ensure that an incorrect program cannot cause other programs to execute incorrectly.
- Provide hardware support to differentiate between at least two modes of operations.
  - 1. User mode execution done on behalf of a user.
  - 2. *Monitor mode* (also *kernel mode* or *system mode*) execution done on behalf of operating system.






## I/O Protection


- All I/O instructions are privileged instructions.
- Must ensure that a user program could never gain control of the computer in monitor mode (I.e., a user program that, as part of its execution, stores a new address in the interrupt vector).


702



### **Memory Protection**

- Must provide memory protection at least for the interrupt vector and the interrupt service routines.
- In order to have memory protection, add two registers that determine the range of legal addresses a program may access:
  - Base register holds the smallest legal physical memory address.
  - ◆ Limit register contains the size of the range
- Memory outside the defined range is protected.







#### **Hardware Protection**

- When executing in monitor mode, the operating system has unrestricted access to both monitor and user's memory.
- The load instructions for the *base* and *limit* registers are privileged instructions.



2.2

Silberschatz, Galvin and Gagne ©2002





#### **CPU Protection**

- *Timer* interrupts computer after specified period to ensure operating system maintains control.
  - Timer is decremented every clock tick.
  - When timer reaches the value 0, an interrupt occurs.
- Timer commonly used to implement time sharing.
- Time also used to compute the current time.
- Load-timer is a privileged instruction.



